

<b>Activate Server</b>		<b>OS:</b> NetWare 4
<b>Description:</b>	Manages different tasks regarding the SFT III server in NetWare. Loads the MSEngine, synchronizes between the two servers, remirrors two servers, and runs <code>msstart.ncf</code> and <code>msauto.ncf</code> .	
<b>Syntax:</b>	activate server [ option ]	
-na	Doesn't execute the <code>msauto.ncf</code> file while starting the MSEngine.	
-ns	Doesn't execute the <code>msstart.ncf</code> file while starting the MSEngine.	
-na-ns	Executes either the <code>msauto.ncf</code> or <code>msstart.ncf</code> files while starting the MSEngine.	

<b>adaptec</b>		<b>OS:</b> NetWare 3
<b>Description:</b>	Installs the Adaptec DIBI-2 tape drivers for use with Cheyenne backup software.	
<b>Syntax:</b>	load adaptec port= <i>port</i> buffer= <i>value</i>	
port= <i>port</i>	Specifies the port number for Adaptec SCSI host adapter (default is 330).	
buffer= <i>value</i>	Specifies the number of buffers to allocate. Each buffer is 64k (default is 6).	
<b>File Name:</b>	<code>adaptec.nlm</code>	<b>Directory:</b> \system <b>Type:</b> External

<b>addicon</b>		<b>OS:</b> NetWare 4
<b>Description:</b>	Adds icons to Windows 3.1x Program Manager groups.	
<b>Syntax:</b>	addicon { <i>parameters...</i> } [ @ <i>scriptfile</i> ] [ option ]	
icon= <i>filename</i>	Specifies a .exe file containing an icon (default is EXE file).	
exe= <i>filename</i>	Specifies the .exe file.	
desc= <i>text</i>	Specifies the description to the executable file (default is the EXE file).	
cmd= <i>parameters</i>	Specifies command-line parameters.	
work= <i>directory</i>	Specifies the working directory of the file.	
min=yes   no	Sets the minimize flag (default is NO).	
group= <i>groupname</i>	Specifies which program group to modify (default is Startup).	
windows= <i>path</i>	Specifies the path to the Windows directory.	
groupfile= <i>filename</i> .GRP	NOTE: If not specified, <code>addicon</code> searches for <code>win.com</code> . Specifies which .GRP file to update.	
@ <i>scriptfile</i>	Specifies a file that contains parameters. NOTE: If <code>scriptfile</code> is specified, all other parameters are ignored.	
/H	Shows help information.	
/S	Quiet mode. Doesn't dump any messages.	
<b>File Name:</b>	<code>addicon.exe</code>	<b>Directory:</b> \public <b>Type:</b> External

<b>afp</b>		<b>OS:</b> NetWare 3,4
<b>Description:</b>	Allows Macintosh users to share files and applications with users on other platforms. After loading AFP, load the AFPCON utility to configure the AppleTalk filing protocol.	
<b>Syntax:</b>	load afp	
<b>File Name:</b>	<code>afp.nlm</code>	<b>Directory:</b> \system <b>Type:</b> External

<b>afpcon</b>		<b>OS:</b> NetWare 4
<b>Description:</b>	Configures the AppleTalk Filing Protocol module.	
<b>Syntax:</b>	load afpcon	
Quick Configuration	Configures AppleTalk Filing Protocol to default values.	
Detailed Configuration	Shows and specifies all AppleTalk Filing Protocol parameters.	
Maintenance and Status	Starts and stops the AppleTalk Filing Protocol services.	
<b>File Name:</b>	<code>afpcon.nlm</code>	<b>Directory:</b> \system <b>Type:</b> External

<b>alert</b>		<b>OS:</b> NetWare 5,6
<b>Description:</b>	Enables or disables specific aspects of alert messages. User can limit the amount of information displayed with an alert message.	
<b>Syntax:</b>	alert <i>nmlD</i> command ON or OFF	
<i>nmlD</i>	Specifies <i>nmlD</i> number of an alert to manage.	
<i>command</i>	Specifies which command to use. Use one of the following:	

event	Generates an event when the alert is created.
log	Sends the alert to a log file.
everyone	Sends the alert to everyone on the network.
console	Shows the alert on the server console.
bell	Makes an alert bell sound when the alerts is generated.
id	Shows ID information. Appears in some older alerts, but is no longer used.
locus	Shows locus information. Appears in some older alerts, but is no longer used.
alert	Generates the alert.
nmID	Shows the alert's nmID in the alert message.
all	Enables or disables the log, everyone, consoles, and bell commands at the same time.
ON or OFF	Specifies whether to turn the alert ON or OFF for the specified command.
<b>TIP:</b>	Use <code>alert</code> to disable less important alert messages.
alert 40018 all on	Enables the log, everyone, console, and bell commands on all alerts with nmID 40018.

<b>allow</b>		<b>OS:</b> NetWare 3
<b>Description:</b>	Shows, sets or modifies the Inherited Rights Mask for a specified file or directory.	
<b>Syntax:</b>	allow { <i>path</i> } <i>rights</i>	
<i>path</i>	Specifies the path to the directory.	
<i>rights</i>	Specifies the rights for the directory. <b>The following rights can be combined separated by spaces.</b>	
All	Sets the rights to all eight trustee rights.	
N	Sets the rights to no rights.	
S	Allows users all rights to directories, files and subdirectories.	
R	Allows users to open and read files.	
W	Allows users to open and write to files.	
C	Allows users to create and write to files.	
E	Allows users to erase directories, files and subdirectories.	
M	Allows users to rename and alter the attributes of directories and files.	
F	Allows users to see files in a directory.	
A	Allows users to alter the trustee assignments and Inherited Rights Masks of files.	
<b>File Name:</b>	allow.exe	<b>Directory:</b> \public <b>Type:</b> External
<b>NOTE:</b>	Remember to use a space between each option.	
allow UCG.* R W E M	Sets the rights of all files beginning with UCG to Read, Write, Erase and Modify.	

<b>appletviewer, applet</b>		<b>OS:</b> NetWare 5, 6
<b>Description:</b>	Runs Java applets on the NetWare server console.	
<b>Syntax:</b>	appletviewer [ options.. ] <i>applet</i>	
-debug	Shows debug information.	
-Jflags	Specifies Java runtime flags.	
<i>applet</i>	Specifies the applet as a file or a URL address	
<b>NW6</b>		
-encoding <i>type</i>	Specifies the character encoding type to use.	
<b>NOTE:</b>	The <code>java.nlm</code> must be loaded to use this command.	
<b>File Name:</b>	aconsole.exe	<b>Directory:</b> \public <b>Type:</b> External

<b>atconfig</b>		<b>OS:</b> NetWare 4
<b>Description:</b>	Configures the AppleTalk protocol on the NetWare server after AppleTalk was implemented.	
<b>Syntax:</b>	load atconfig	
<b>File Name:</b>	atconfig.nlm	<b>Directory:</b> <b>Type:</b> External

<b>ATM Console</b>		<b>OS:</b> NetWare 5
<b>Description:</b>	Starts a tool used for troubleshooting and monitoring ATM network traffic.	
<b>Syntax:</b>	atmcon	
Link/ATM Network Interfaces	Shows a list of ATM networks.	

<b>File Name:</b>	atmcon.nlm	<b>Directory:</b>	\system	<b>Type:</b>	External
-------------------	------------	-------------------	---------	--------------	----------

<b>atotal</b>		<b>OS:</b>	NetWare 3,4,5
<b>Description:</b>	Compiles accounting information and shows daily and weekly totals for connection time, service requests, number of blocks read and written, and the disk storage utilized per day.		
<b>Syntax:</b>	atotal [ > file ] [ options... ]		
/c	Doesn't pause after each screen. Scrolls continuously.		
/?	Shows help information.		
file	Specifies the path and file name to redirect the accounting information.		
<b>NW4, NW5:</b>			
/ver	Shows utility version number and a list of all files it uses to execute.		
<b>File Name:</b>	atotal.exe	<b>Directory:</b>	NW3:\system, NW4, NW5: \public
<b>NOTE:</b>	Accounting services must be active on server for atotal to work.		
atotal >n:\ucg	Redirects the output of atotal to the file ucg on n:.		

<b>atpscon</b>		<b>OS:</b>	NetWare 4
<b>Description:</b>	Configures the AppleTalk printing service on NetWare server.		
<b>Syntax:</b>	load atpscon		
Quick Configuration	Creates spooler, queue, and print server with default values.		
Configure Printer Servers	Specifies a print server on AppleTalk that connects to a print server in NetWare.		
Define Printer Models	Specifies printers of a new type.		
Log Options	Shows and configures system and printer logs.		
Management Options	Configures AppleTalk Printing Service regarding fonts and internal files.		
Change Context	Changes the position in the NDS tree.		

<b>attach</b>		<b>OS:</b>	NetWare 3
<b>Description:</b>	Connects to another file server and still remain logged on to your current file server.		
<b>Syntax:</b>	attach { server } { username }		
server	Specifies the name of the file server to attach to.		
username	Specifies the username to use on the file server.		
<b>File Name:</b>	attach.exe	<b>Directory:</b>	\public
attach UCG/Myles	Attaches to the file server UCG as user Myles.		

<b>atxrp</b>		<b>OS:</b>	NetWare 4
<b>Description:</b>	Connects a driver to pserver that lets users connected to the NetWare server print on AppleTalk printers.		
<b>Syntax:</b>	load atxrp		

<b>auditcon</b>		<b>OS:</b>	NetWare 4,5
<b>Description:</b>	Tracks a users activity on the server regarding applications, files transferred or printers the user has used and produces a report that can be submitted for billing purposes.		
<b>Syntax:</b>	auditcon [ /VER ]		
/VER	Shows version information.		
<b>File Name:</b>	auditcon.exe	<b>Directory:</b>	\public
		<b>Type:</b>	External

<b>bindfix</b>		<b>OS:</b>	NetWare 3
<b>Description:</b>	Corrects the data in the bindery files if the file has been corrupted. It creates new versions of the files NET\$OBJ.SYS, NET\$PROP.SYS, and NET\$VAL.SYS. The old files are saved with .old extension.		
<b>Syntax:</b>	bindfix		
<b>File Name:</b>	bindfix.exe	<b>Directory:</b>	\system
		<b>Type:</b>	External